



Transforming the Buy-side Experience

Installation guide and system requirements



Neovest (Desktop) installation guide

Pages 03 - 07

Step by step walkthrough of the Neovest installation wizard.

System requirements & firewall setup

Pages 08 - 12

Recommended PC hardware specifications.

Ports and IPs you will have to open on your firewall to connect.

Remote Router Servers (RRS) specifications.

How to access UAT

Pages 13 - 14

Instructions to log into the Neovest simulation environment.

New York | Orem | London | Hong Kong | Singapore | Sydney

© 2024 Neovest, Inc. All rights reserved. This material is provided for informational purposes only and is subject to change without notice. Neovest, Inc. and its affiliates disclaim all responsibility and liability whatsoever for the non-infringement, accuracy, currency and completeness of the information herein and for any reliance on, or use of, this material in any way. Neovest, Inc. is a subsidiary of JPMorgan Chase & Co. Product names, company names and logos mentioned herein are trademarks or registered trademarks of their respective owners.

Neovest (Desktop) installation guide

Step 1: Download the Neovest installer

To download the Neovest installer from our secured website please click on the link below:

<https://support.neovest.com/Install/neovest/NeovestSetup64.exe>

Step 2: Run the installer



The Neovest installer should be run by a user that has “administrator” rights on the machine.

 NeovestSetup64



New York | Orem | London | Hong Kong | Singapore | Sydney

© 2024 Neovest, Inc. All rights reserved. This material is provided for informational purposes only and is subject to change without notice. Neovest, Inc. and its affiliates disclaim all responsibility and liability whatsoever for the non-infringement, accuracy, currency and completeness of the information herein and for any reliance on, or use of, this material in any way. Neovest, Inc. is a subsidiary of JPMorgan Chase & Co. Product names, company names and logos mentioned herein are trademarks or registered trademarks of their respective owners.

Below is a step by step view of the Neovest installation wizard.





New York | Orem | London | Hong Kong | Singapore | Sydney



New York | Orem | London | Hong Kong | Singapore | Sydney

Please select the region that is closest to the location of the user.



New York | Orem | London | Hong Kong | Singapore | Sydney

Step 3: Login into production

You should now see a Neovest icon on your desktop.



Once you launch Neovest a login window will appear.



The **User Name** and **Domain** will be provided by the Neovest team during onboarding.

The **Password** is set by the users themselves during the onboarding process. An email will be sent to them privately, inviting them to create their password and set up security questions.

New York | Orem | London | Hong Kong | Singapore | Sydney

System Requirements

Client machines must have the following specifications.

Recommended:

- ✓ Windows 10 (64-bit)
- ✓ Intel quad-core i7 or better
- ✓ 16GB RAM
- ✓ 5GB free Disk Space
- ✓ 30M Available Bandwidth to our datacenter(s)*

*Dedicated bandwidth – amount depends on usage.

Quant or basket trading firms should contact us to discuss bandwidth requirements.

New York | Orem | London | Hong Kong | Singapore | Sydney

© 2024 Neovest, Inc. All rights reserved. This material is provided for informational purposes only and is subject to change without notice. Neovest, Inc. and its affiliates disclaim all responsibility and liability whatsoever for the non-infringement, accuracy, currency and completeness of the information herein and for any reliance on, or use of, this material in any way. Neovest, Inc. is a subsidiary of JPMorgan Chase & Co. Product names, company names and logos mentioned herein are trademarks or registered trademarks of their respective owners.

Firewalls – Production

To access Neovest’s production datacentres the following IP addresses will need to be opened on **Port 5600**.

IP	Host	Port	Location
199.36.68.10	directfeed2.neovest.com	5600	United States
199.36.71.10	directfeed.neovest.com	5600	United States
205.217.20.201	ukdirectfeed.neovest.com	5600	United Kingdom
34.126.150.5	md-sg.neovest.com	5600	Singapore

The following IP addresses will need to be opened on **Ports 9793, 9794 & 9797**.

IP	Host	Port	Location
199.36.68.14	savoe1.neovest.com	9793 9794	United States
199.36.68.15	savoe2.neovest.com	9793 9794 9797	United States
199.36.71.15	oe.us2.neovest.com	9793 9794	United States
205.217.20.202	ukoe.neovest.com	9793 9794	United Kingdom
34.126.189.240	oe-sg.neovest.com	9794	Singapore
34.126.159.82	oea-sg.neovest.com	9797	Singapore

HTML content will go over https port **443** with ***.prod.neovest.com** DNS.

New York | Orem | London | Hong Kong | Singapore | Sydney

Firewalls – UAT

To access Neovest’s UAT/Simulation environment, the following IP addresses will need to be opened on **Port 5600**.

IP	Host	Port	Location
199.36.68.141	directfeedsim.neovest.com	5600	United States

The following IP addresses will need to be opened on **Ports 9798**.

IP	Host	Port	Location
199.36.68.16	oesim.neovest.com	9798	United States

HTML content will go over https port **443** with ***.sim.neovest.com** DNS.

New York | Orem | London | Hong Kong | Singapore | Sydney

Firewalls – Remote Router Server (RRS)

The section below is only relevant for clients who setup a Remote Router Server with Neovest.

To access Neovest’s Remote Router Servers the following IP addresses will need to be opened on **Port 5600**.

IP	Host	Port	Location
199.36.68.11	directfeed2rrs.neovest.com	5600	United States
199.36.71.11	directfeedrrs.neovest.com	5600	United States
205.217.20.203	ukdirectfeedrrs.neovest.com	5600	United Kingdom
34.126.127.243	rrs-sg.neovest.com	5600	Singapore

New York | Orem | London | Hong Kong | Singapore | Sydney

Remote Router Server (RRS) – System Requirements

Recommended:

- ✓ Windows Server 2016 R2 64-bit
- ✓ Xeon processor with 8 cores
- ✓ 16GB+ RAM
- ✓ 100GB available disk space
- ✓ Physical Server with Hyperthreading disabled

For additional information, please contact your account manager or support@neovest.com

Americas	+1 800 433 4276
EMEA	+44 808 189 0330
APAC	+852 800 906 160

New York | Orem | London | Hong Kong | Singapore | Sydney

Login into Neovest' s UAT/simulation environment

UAT/simulation logins allow users to submit dummy orders to get used to the look and feel of Neovest.

Please contact your Neovest account manager if you need access to UAT/simulation logins.

To login into UAT/simulation you will have to set your Neovest to point towards our UAT servers.

Upon launching Neovest click on "Setup".



New York | Orem | London | Hong Kong | Singapore | Sydney

© 2024 Neovest, Inc. All rights reserved. This material is provided for informational purposes only and is subject to change without notice. Neovest, Inc. and its affiliates disclaim all responsibility and liability whatsoever for the non-infringement, accuracy, currency and completeness of the information herein and for any reliance on, or use of, this material in any way. Neovest, Inc. is a subsidiary of JPMorgan Chase & Co. Product names, company names and logos mentioned herein are trademarks or registered trademarks of their respective owners.

Select **Simulated Trading**.

Populate the **Host** and **Port** details as per below and click "OK".

Authentication Server


Host: directfeedsim.neovest.com
Port: 5600

Order Entry Server

Host: oesim.neovest.com
Port: 9798

App Server

Host: nj2x.sim
Port: No port is needed



Neovest will now state **Simulated Trading Environment** in red on the login window.

You are ready to login into simulation.



New York | Orem | London | Hong Kong | Singapore | Sydney